Phosphorus Management in the Chesapeake Bay Watershed


Pete Kleinman

USDA-ARS University Park, PA





2009 Executive Order 13508 2011 Chesapeake Bay TMDL




TMDL goal – 15 million lbs P/yr 92 TMDLs 44,000 farms 17 million people 483 treatment plants \$2.36 billion federal funds to 2011

64,000 sq-miles




\equiv

Long term causes Regional nutrient imbalance





Pennsylvania cropland P balance 1939-2002







The Beaver Stadium 108,000 Nittany Lion fans

100,000,000 gallons = 378,000,000 liters



Chesapeake Bay Watershed -

Livestock
(1.7 million au)
44 million tons
manure

100 Beaver stadiums

14 million humans4 million tons

10



Manure export = P export

Delmarva litter pelletizing plant

Dane County
Wisconsin
manure digester


Minnesota turkey litter power plant

Arkansas poultry litter baling






Benefit - agricultural BMPs



Expected P reductions





Casualty – Nutrient Management Planning Chesapeake Bay Guidance for Federal Land Management

- Replace P Index with soil environmental threshold (soil P saturation)
 - > 20% Psat, no added P
 - <20% Psat, up to N-basis
 - If Psat 1, P-basis
- 2. Need other tools to deal with hydrology, including reimplementing P Index.







Nutrient Management Planning – 1999 NRCS Uniform Strategy Field Management of P

- 1. Soil threshold agronomic
- 2. Soil threshold environmental
- 3. Site assessment tool P Index





P Index – Identifies Critical Source Areas



P Index – Identifies Critical Source Areas

The Pennsylvania Phosphorus Index

Version 2

PART A: Screening Tool		CMU/Field ID				\neg	
Is the CMU/field in a special protection watershed?		CMO/FIEIG ID					

P Index – Identifies Critical Source Areas

Site Conditions

Source

- Soil P
- Manure (rate, method, timing)
- Fertilizer (rate, methods, timing)

Transport

- Runoff
- Erosion
- Leaching


Site Rating



Table 2. Phosphorus index management guidance


Value	Rating	Management Guidance
0 to 59	Low	Nutrients can be applied to meet the nitrogen crop requirement.
		Low potential for P loss. Maintenance of current farming practices is recommended to minimize the risk of adverse impacts on surface waters.
60 to 79	Medium	Nutrients can be applied to meet the nitrogen crop requirement.
		Medium potential for P loss. The chance for adverse impacts on surface waters exists. An assessment of current farm nutrient management, and conservation, practices is recommended to militarize the risk of tuture P loss.
80 to 99	High	Nutrients can be applied to meet the phosphorus crop removal.
		High potential for P loss and adverse impacts on surface waters. Soil and water conservation measures and P-based management plans are needed to minimize the risk of P loss.
100 or	Very High	No phosphorus can be applied.
		Very high potential for P loss and greater adverse impacts on surface waters. Conservation measures and a P-based measurement plan must be implemented to minimize the P loss.

Soil P saturation – Indicator of runoff P



Soil P saturation – soil indicator only <1 kg/ha/yr Psat = 21% 1 kg/ha/yr 8 kg/ha/yr Psat = 17% Psat = 9% Buda et al. (2009) - J. Environ. Qual.

Soil P saturation – manipulated by tillage/sampling depth







Survey of fields where the Maryland P Index was i

IV > 150 only)

P Management Future

- 1. More stringent field restrictions
- 2. Regional manure management
 - Chesapeake P Index?
 - Manure transport/export
- 3. Improved representation of hydrology/transport
 - Leaching
 - Forecasting
 - Erosion LiDAR DEMs
- 4. Dedicated practices
 - Legacy P



THANK YOU

